greenerthumb ICD

- Timestamps are 8-byte unix timestamps.
- Sender is the name of the package who sent the message. Multiple hosts can share a sender. This means the hosts are in the same package.
- Checksums are cyclic sums of all of a message's bytes excluding the checksum
- Multi-byte fields are big-endian.
- All messages start the header.
- All messages are newline-terminated across the network for simplicity.

Header

Byte	Name	Type
1	ID	Byte
2	Timestamp	Long
10	Sender Length (n)	Byte
11	Sender	Byte Sequence

Air Status Message (pub/sub, ID = 0x00)

Byte	Name	Type
1	Temperature	Float
5	Checksum	Byte

• Temperature is in degrees fahrenheit.

Soil Status Message (pub/sub, ID = 0x01)

Byte	Name	Type
1	Moisture	Float
5	Checksum	Byte

• Moisture is the ratio of water to soil.

Disclosure Message (Broadcast on port 35053 by default, ID = 0x02)

Byte	Name	Type
1	Host Length (n)	Byte
2	Host	Byte Sequence
2 + n	Checksum	Byte

• Host is the host the device publishes to.

JSON

JSON is used for internal messaging. Every message has a corresponding JSON format with the structure:

```
{
   "Header": {
      "Name": <message_name>,
      "Timestamp": <timestamp>,
      "Sender": <sender>
   },
   <name>: <value>,...
}
```

IDs are swapped with names for friendlier use in applications. Checksums are excluded since the messages don't need to be sent over a network. Names and values correspond to the non-ID, non-time, and non-checksum fields in the messages.